

Insurance Plan Code		90 Actual Production History						
Commodity Code	0012 Blueberries	0047 Dry Beans		0089 Pears		0223 Fresh Freestone Peaches		
	0013 Onions	0049 Safflower		0092 Fresh Plums		0224 Early & Midseason Oranges		
	0016 Oats	0052 Table Grapes		0094 Rye		0225 Late Oranges		
	0017 Millet	0053 Grapes		0107 Alfalfa Seed		0226 All Other Grapefruit		
	0019 Avocados	0054 Apples		0114 Buckwheat		0228 Ruby Red Grapefruit		
	0022 Cotton Extra Long	0055 Culti Wild Rice		0147 Pumpkins		0229 Flue Cured Tobacco		
	0023 Macadamia Nuts	0058 Cranberries		0201 Grapefruit		0230 Fire Cured Tobacco		
	0028 Almonds	0059 Silage Sorghum		0202 Lemons		0231 Burley Tobacco		
	0029 Walnuts	0060 Figs		0205 Mandarins		0232 Maryland Tobacco		
	0031 Flax	0064 Green Peas		0206 Minnelo Tangelos		0233 Dark Air Tobacco		
	0033 Forage Production	0067 Dry Peas		0215 Navel Oranges		0234 Cigar Filler Tobacco		
	0034 Peaches	0069 Mustard		0216 Sweet Oranges		0235 Cigar Bindr Tobacco		
	0036 Prunes	0072 Cabbage		217 Valencia Oranges		0236 Cigar Wrapper Tobacco		
	0038 Sugar Cane	0074 Mint		0218 Fresh Apricots		0237 Orlando Tangelos		
	0039 Sugar Beets	0075 Peanuts		0219 Processing Apricots		0238 Rio Red & Star Ruby		
	0042 Sweet Corn	0084 Potatoes		0220 Fresh Nectarines		0255 Banana		
	0043 Popcorn	0086 Fresh Tomatoes		0221Processing Cling Peaches		0256 Coffee		
	0046 Canning Beans	0087 Tomatoes		0222 Processing Freestone		0257 Papaya		
	Calculations		Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
	Section 1: Stage Guarantee Calculation							
When Units Of Measure equals LBS, "09":								
Guarantee Per Acre1 = Approved Yield * Coverage Level Percent		Guarantee Per Acre1	Internal		99999999.99	Round to whole number.		
		Approved Yield	P11	47	99999999.99	None		
		Coverage Level Percent	P14	33	9.9999	None		
Premium Acre Guarantee Quantity = Guarantee Per Acre1 * Guarantee Adjustment Factor		Premium Acre Guarantee Quantity	Internal		99999999.99	Round to whole number.		
		Guarantee Adjustment Factor	P11	41	0.999	None		
Acre Stage Guarantee Amount = Premium Acre Guarantee Quantity * Stage Percent Factor		Acre Stage Guarantee Amount	P21	36	99999999.99	Round to whole number.		
		Stage Percent Factor	ICE		999.99	None	Edit with ICE Stage Factor, "D00069".	
When Units Of Measure equals Tons, "12":								
Guarantee Per Acre1 = Approved Yield * Coverage Level Percent		Guarantee Per Acre1	Internal		99999999.99	Round to 2 decimals.		
		Approved Yield	P11	47	99999999.99	None		
		Coverage Level Percent	P14	33	9.9999	None		

Calculations	Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
Premium Acre Guarantee Quantity = Guarantee Per Acre1 * Guarantee Adjustment Factor	Premium Acre Guarantee Quantity	Internal		99999999.99	Round to 2 decimals.	
	Guarantee Adjustment Factor	P11	41	0.999		
Acre Stage Guarantee Amount = Premium Acre Guarantee Quantity * Stage Percent Factor	Acre Stage Guarantee Amount	P21	36	99999999.99	Round to 2 decmials.	
	Stage Percent Factor	ICE		999.99	None	Edit with ICE Stage Factor, "D00069".
For all other Units of Measure:  Guarantee Per Acre1 = Approved Yield * Coverage Level Percent * Historical Packout Factor	Guarantee Per Acre1	Internal		99999999.99	Round to 1 decmial.	
	Approved Yield	P11	47	99999999.99	None	
	Coverage Level Percent	P14	33	9.9999	None	
	Historical Packout Factor	Internal		9.999	None	
Guarantee Per Acre2 = Guarantee Per Acre1 * Yield Conversion Factor	Guarantee Per Acre2	Internal		99999999.99	Round to 1 decmial.	
	Yield Conversion Factor	P11	62	9.999	None	
Premium Acre Guarantee Quantity = Guarantee Per Acre2 * Guarantee Adjustment Factor	Premium Acre Guarantee Quantity	Internal		99999999.99	Round to 1 decmial.	
	Guarantee Adjustment Factor	P11	41	0.999		
Acre Stage Guarantee Amount = Premium Acre Guarantee Quantity * Stage Percent Factor	Acre Stage Guarantee Amount	P21	36	99999999.99	When Units Of Measure equals Cartons, "04" or Hundredweight, "08", then round to 1 decimals.  Otherwise round to 2 decimals.	
	Stage Percent Factor	ICE		999.99	None	Edit with ICE Stage Factor, "D00069".
Section 2: Loss Guarantee Calculation						
Loss Guarantee Amount = Acre Stage Guarantee Amount * Determined Acreage * Liability Adjustment Factor	Loss Guarantee Amount	P21	49	99999999.99	When Unit of Measure equals Barrels, "01" or Pounds, "09" then round to 1 decimal.  Otherwise, round to whole number.	
	Determined Acreage	P21	17	99999999.99	None	
	Liability Adjustment Factor	P21	40	9.999999	None	

Calculations	Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
Section 3: Indemnity Calculation						
Unit Deficiency Quantity = $\frac{\text{Loss Guarantee Amount} - \text{Production to Count Quantity}}{\text{Quantity}}$	Unit Deficiency Quantity	P21	35	\$99999999.99	When Units of Measure equals Dollars, "07" or Pounds, "09" then round to whole number.  Otherwise, round to 1 decimal.	
	Production to Count Quantity	P21	34	99999999.99	None	
Preliminary Indemnity Amount = $\frac{\text{Unit Deficiency Quantity} * \text{Price Election Percent}}{\text{Stage Percent Factor} * \text{Insured Share Percent}}$	Preliminary Indemnity Amount	P21	52	\$9999999999	Round to whole number.	
	Price Election Percent	ICE		9.9999	None	Edit with ICE Price Election Percent, "D00007".
	Stage Percent Factor	ICE		999.99	None	Edit with ICE Stage Factor, "D00069".
	Insured Share Percent	P11	46	9.999	None	
Indemnity Amount = $\frac{\text{Preliminary Indemnity Amount} * \text{Multiple Commodity Adjustment Factor}}{\text{Adjustment Factor}}$	Indemnity Amount	P21	53	\$9999999999	Round to whole number.	
	Multiple Commodity Adjustment Factor	ICE		9999.999	None	Edit with ICE Multiple Cropping, "D00063".
When CEO Coverage Level is greater than zero:  CEO Indemnity Factor = $\frac{\text{CEO Coverage Level}}{\text{Coverage Level Percent}}$	CEO Indemnity Factor	P21	48	9.99999	Round to 5 decimals.	
	CEO Coverage Level	ICE		9.9999	None	Edit with ICE Coverage Level, "D00054".
	Coverage Level Percent	P14	33	9.9999	None	
Indemnity Amount = Indemnity Amount * CEO Indemnity Factor	Indemnity Amount	P21	53	\$9999999999	Round to whole number.	

Calculations	Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
Section 4: Replant Payment Guarantee Calculation						
When Stage Code equals:    Replanted, "R", Replanted Seed, "RS", Replanted Transplant, "RT"  Stage Guarantee Per Acre = Maximum Replant Guarantee Per Acre	Stage Guarantee Per Acre	P21	50	99999999.99	Round to whole number.	When Commodity Code is Popcorn, "0043", Rice, "0018", Fresh Market Tomatoes, "0086", or Peanuts, "0075".
Guarantee per Acre1 = Approved Yield * Coverage Level Percent	Guarantee Per Acre1	Internal		99999999.99	When Units of Measure equal Pounds, "09" then round to whole number.  When Units of Measure equals Tons, "12" then round to Hundredths,  Otherwise, for all other Units of Measure, round to Tenths	
	Approved Yield	P11	47	99999999.99	None	
	Coverage Level Percent	P14	33	9.9999	None	
Premium Acre Guarantee Quantity = Guarantee Per Acre1 * Guarantee Adjustment Factor	Premium Acre Guarantee Quantity	Internal		99999999.99	When Units of Measure equal Pounds, "09" then round to whole number.  When Units of Measure equals Tons, "12" then round to Hundredths,  Otherwise, for all other Units of Measure, round to Tenths	
	Guarantee Adjustment Factor	P11	41	0.999	None	Guarantee Adjustment Factor must equal 1.000 when Commodity Code is Peanuts, "0075".

Calculations	Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
<div>Acre Stage Guarantee = Premium Acre Guarantee Quantity * Stage Percent Amount = Factor</div>	Acre Stage Guarantee Amount	P21	36	99999999.99	<div>When Units of Measure equal Pounds, "09" then round to whole number.</div> <div>When Units of Measure equals Tons, "12" then round to Hundredths,</div> <div>Otherwise, for all other Units of Measure, round to Tenths</div>	
	Stage Percent Factor	ICE		999.99	None	<div>Stage Percent Factor equals 0.10, when Commodity Code is Dry Beans, "0047", Sugar Beets, "0039".</div> <div>Stage Percent Factor equals 0.25 when Commodity Code is Tomatoes, "0087".</div> <div>Stage Percent Factor equals 0.22 when Commodity Code is Onions, "0013" in Location State Code, New York, "36". For all other Location States, Stage Percent Factor equals 0.07.</div> <div>Otherwise, Stage Percent Factor equals 0.20.</div> <div>Edit with ICE Stage Factor, "D00069".</div>

Calculations	Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
Section 5: Replant Payment Loss Guarantee Calculation						
Loss Guarantee Amount = $\frac{\text{Acre Stage Guarantee Amount} * \text{Determined Acreage}}{\text{Liability Adjustment Factor}}$	Loss Guarantee Amount	P21	49	99999999.99	When Unit of Measure equals Barrels, "01" or Tons, "12" then round to 1 decimal.  Otherwise, round to whole number.	
	Determined Acreage	P21	17	99999999.99	None	
	Liability Adjustment Factor	P21	43	9.999999	None	
Section 6: Replant Payment Indemnity Calculation						
Indemnity Amount = $\frac{\text{Loss Guarantee Amount} * \text{Price Election Amount}}{\text{Insured Share Percent}}$	Indemnity Amount	P21	53	S9999999999	Round to whole number.	
	Price Election Amount	ADM		9.9999	None	Price Election Amount equals 1.000 when Commodity Code equals Peanuts, "0075".  Edit with the Price ADM, "A00810".
	Insured Share Percent	P11	48	9.999	None	